

EzRemote 1.0 Manual

1. Configure a Connection

To setup a connection, you need to input the following information:

- a. **Name:** the name displayed in the server list
- b. **Host or IP:** the name or IP address of the computer you want to connect
- c. **Port:** the TCP/IP port used for RDP. If you don't know, use the default one (3389), or consult your network administrator
- d. **Size:** use these parameters to specify the desktop resolution.
- e. **User Name:** specify the user name for this server connection
- f. **Password:** specify the password for this server connection

In order to connect server, select either **connect-16 bit** or **connect-8bit** buttons. To disconnect from server, select **Disconnect** or use shortcut **/D**.

2. Server Setup

There is no additional software to install on the server. However, before using EzRemote, you may need to enable Remote Desktop Connection (for XP) or Windows Terminal Service (for Windows NT, 2000 server, and 2003 server). It is easy to setup, which only needs 3 steps:

1. Go to the **System** folder (**start -> settings -> control panel -> system**)
2. On the **Remote** tab, select the **Allow users** to connect remotely to this computer. The user selected must have a password. (You can setup users in control panel - User Accounts)
3. Make sure that user has proper permission to connect to your computer remotely, and click OK.

For detailed information, please refer to following links:

- **Windows XP Professional:**

<http://www.microsoft.com/windowsxp/using/mobility/default.aspx>

- **Windows 2000 Server:**

<http://www.microsoft.com/windows2000/technologies/terminal>

- **Windows Server 2003:**

<http://www.microsoft.com/windowsserver2003/community/centers/terminal>

3. Navigate the Virtual Screen

EzRemote provides several ways to make it easier to navigate the virtual screen.

- a. **Fit-to-Screen:** you can use **home** button to toggle Fit-to-Screen (**Treo Phone On**)
- b. **One-touch-focus:** In Fit-to-Screen mode, the EzRemote will focus on the area of next click on the screen

- c. **Pan:** the **date book** button is used to toggle the pan mode and you can use stylus go pan your virtual screen (Treo **Date Book** Button)

4. Quick Buttons

- a. **5-way navigator:** map to the up, down, left, right and enter on the server (Treo same)
- b. **Contact button:** map to the right mouse button (Treo Phone Off)
- c. **Application button:** map to the Esc key (Treo Mail Button)

(Note: key mapping is different on a Treo)

5. Menu

- a. **Winkey:** send winkey to the server
- b. **Ctrl-alt-del:** send ctrl-alt-del to the server
- c. **Restart computer:** restart the remote computer
- d. **Disconnect:** disconnect from remote server

6. Regeistration

To reduce piracy, when you buy EzRemote, it is locked (registered) to a handheld with "Device ID" and "Hotsync Username". EzRemote generates a unique registration ID for your Device. To get your

registration ID, please run EzRemote and then click on the "Menu" and choose Options->Register in the pull-down menu. After sending your "Device ID" and "Hotsync Username", your registration information will be sent to you by e-mail in 1-2 business days.